






Stop IIS Admin Service.







Adjust C:\Windows\System32\inetmgr\MetaBase.xml

In the section **<IISSmtpServer Location ="/LM/SmtpSvc/1"**

Add the following option: **RelayList=""** (note alphabetical sorting)

Now start the IIS Service again.





[SMTP Virtual Server #1] Properties ? X

General Access Messages Delivery LDAP Routing Security

Specify the following messaging information.

☒ Limit message size to (KB): 9216

☒ Limit session size to (KB): 10240

☒ Limit number of messages per connection to: 20

☒ Limit number of recipients per message to: 100

Send copy of Non-Delivery Report to:

Badmail directory:
C:\inetpub\mailroot\Badmail Browse...

Username and password is of the SMTP Server of the Customer

[SMTP Virtual Server #1] Properties ? X

General Access Messages Delivery LDAP Routing Security

Outbound

First retry interval (minutes): 15

Second retry interval (minutes): 30

Third retry interval (minutes): 60

Subsequent retry interval (minutes): 240

Delay notification: 12 Hours

Expiration timeout: 2 Days

Local

Delay notification: 12 Hours

Expiration timeout: 2 Days

Outbound Security

☐ Anonymous access
No user name or password required.

☒ Basic authentication
The password will be sent over the network in clear text using standard commands.

User name: abdc Browse...

Password:

☐ Integrated Windows Authentication
The client and server negotiate the Windows Security Support Provider Interface.

Account: Browse...

Password:

☒ TLS encryption

OK Cancel Help

[SMTP Virtual Server #1] Properties

General Access Messages Delivery LDAP Routing Security

Outbound

First retry interval (minutes): 15

Second retry interval (minutes): 30

Third retry interval (minutes): 60

Subsequent retry interval (minutes): 240

Delay notification: 12 Hours

Expiration timeout: 2 Days

Local

Delay notification: 12 Hours

Expiration timeout: 2 Days

Outbound Security... Outbound connections... Advanced...

Outbound Connections

☐ Limit number of connections to: 1000

Time-out (minutes): 10

☒ Limit number of connections per domain to: 100

TCP port: 587

OK Cancel Help

[SMTP Virtual Server #1] Properties

General Access Messages Delivery LDAP Routing Security

Outbound

First retry interval (minutes): 15

Second retry interval (minutes): 30

Third retry interval (minutes): 60

Subsequent retry interval (minutes): 240

Delay notification: 12 Hours

Expiration timeout: 2 Days

Local

Delay notification: 12 Hours

Expiration timeout: 2 Days

Outbound Security... Outbound connections... Advanced...

Advanced Delivery

Maximum hop count: 15

Masquerade domain:


Fully-qualified domain name: SARMSDSAPP11 Check DNS


Smart host: smtp.postmarkapp.com

☐ Attempt direct delivery before sending to smart host

☐ Perform reverse DNS lookup on incoming messages

OK Cancel Help





RMS can be switched to localhost. Important: The relay only accepts requests from 127.0.0.1, which means that the relay must be installed on each server.

<u>E-mail server</u>	
SMTP server	localhost
SMTP port	25
User name	
Password	
Sender name	Rotronic Monitoring System Test
Sender address	noreply@processensing.net
Encrypted connection	☐